

# Probes Tab

*The Probes tab in Scope measurement control panel contains Probe connection settings and other general settings for the measurement. It's usually the place where a new measurement parameterization is started.*


# Table of Contents

- 1. Overview ..... 3
- 2. Measurement Info ..... 3
  - 2.1. Measurement Name ..... 3
  - 2.2. Measurement Description ..... 4
- 3. Probe Setup ..... 4
- 4. Primary Measurement Point ..... 4
  - 4.1. Hostname or Address ..... 4
  - 4.2. Custom Port ..... 5
- 5. Secondary Measurement Point ..... 5
  - 5.1. Hostname or Address ..... 5
  - 5.2. Custom Port ..... 5
- 6. Client Settings ..... 5
  - 6.1. User ID ..... 6

## 1. Overview


This tab consists of the following settings groups. Detailed information on each group can be found in the following sections. All groups in this tab, excluding *Measurement Info*, are disabled when a connection to Probe(s) is active. To re-enable the tab for editing, stop the current measurement and disconnect from Probes.

- **Measurement Info**
- **Probe Setup**
- **Primary Measurement Point**
- **Secondary Measurement Point** - Visible when two-point measurement is selected
- **Client Settings** - Visible when advanced settings are enabled



## 2. Measurement Info

The measurement info group contains the basic information of the measurement. While optional, it's a good practice to fill out this information for each measurement.



### 2.1. Measurement Name

The name or title of the measurement. Naming the measurement is optional.



Technical name is a machine-friendly version of measurement name, which is used by Scope to, for example, suggest a filename for settings


## 2.2. Measurement Description

Measurement description is an optional text you can use as you wish, e.g., to describe the measurement scenario or some details in the measurement. The text set here will be part of measurement results, appearing in the results files and results systems like Qosium Storage. It is up to you how to use this.

## 3. Probe Setup

In the Probe setup group, the selection between *single-point measurement* and *two-point measurement* can be made.

- **Single-point measurement** mode uses one Probe to measure a single network node or point
- **Two-point measurement** mode utilizes two Probes to measure a network path




Some measurement result types are not available in single-point measurement



Some options in Scope are visible only when a two-point measurement is selected

## 4. Primary Measurement Point

The primary measurement point group contains connection settings for the Probe installed in the primary measurement point. Qosium Probe must be running and reachable via this address and port. For more information on installing and launching Probes, see [Qosium Probe documentation](#).



### 4.1. Hostname or Address

The address can be either a hostname or an IPv4 address. If the primary Probe is installed on the same PC where Scope is running, use local address `127.0.0.1` or `localhost`.

## 4.2. Custom Port



Visible when advanced settings are enabled

If the primary Probe has been [configured](#) to listen to other than the default Qosium port **8177**, set the correct port number here before connecting.

## 5. Secondary Measurement Point



Visible only when a two-point measurement is selected

The secondary measurement point group contains connection settings for the Probe installed in the secondary measurement point. Qosium Probe must be running and reachable via this address and port. For more information on installing and launching Probes, see [Qosium Probe documentation](#).

Secondary Measurement Point

Hostname or address

☐ Custom port 8177

### 5.1. Hostname or Address

The address can be either a hostname or an IPv4 address. If the secondary Probe is installed on the same PC where Scope is running, use local address **127.0.0.1** or **localhost**.

### 5.2. Custom Port



Visible when advanced settings are enabled

If the secondary Probe has been [configured](#) to listen to other than the default Qosium port **8177**, set the correct port number here before connecting.

## 6. Client Settings



Visible when advanced settings are enabled

Client Settings

User ID 0

## 6.1. User ID

User ID is used to identify this controlling entity and differentiate it from other controlling entities. Setting user ID is typically not needed, except when multiple controlling entities collect measurement results to the same result pool. In that scenario, a user ID can be used to identify the user/device which carried out the measurement since it's saved into the measurement result files.